



FAQ# 26-09180102  
Modified 02/06/02

## **PCRE v2.5 to PCRE v2.6 Upgrade Procedure For COM Customers**

These instructions apply to customers using Parallel Crystal with ASP/IIS, Visual Basic and other COM tools.

Please also refer to the FAQ titled: **Major API Changes from PCRE v2.5 to v2.6**  
[http://www.dynalivery.com/customersupport/faq/2\\_6API-changes.html](http://www.dynalivery.com/customersupport/faq/2_6API-changes.html)

### **Server**

- 1) **Uninstall Parallel Crystal v2.5**
- 2) **Prerequisite Software for a Parallel Crystal v2.6 Server Installation**
  - A. Install MDAC v2.6 from PCRE CD.
    1. Run the PCRE install shield and it will detect the presence of MDAC and if it is not where PCRE expects it to be it will give you the option to install it or exit from the installation. Install the MDAC and reboot.
  - B. Install or update Internet Explorer to version 5.0 or above.
- 3) **Install PCRE v2.6 from the CD.** (see installation guide)

### **Client** (middle tier)

- 1) **Uninstall Parallel Crystal v2.5**
- 2) **Prerequisite Software for a Parallel Crystal v2.6 Client Installation**
  - A. Install Sun's Java Runtime Environment (JRE) v1.2 or the full JDK 1.2.2
  - B. Install Microsoft's Java Virtual Machine (build 3802 or higher)
- 3) **Install PCRE v2.6 client libraries only from the CD.** (see installation guide)